

# Dainty Keychain Wallet Project

www.yoansewingstudio.com

www.youtube.com/yoansewingstudio

©Copyright 2021 Yoan Sewing Studio



## Supplies

Fabric A : 1/6 yard or 1x fat eight

Fabric B : 1/8 yard

\*based on regular 44" wide cotton quilting fabric

\*recommended fabric : cotton quilting, flannel, canvas, light-medium weight linen

6" x 4 1/2" Firm stabilizer or medium-heavy interfacing  
(e.g. decor bond, light decovil, craft fuse)

Note : I use decor bond - Pellon 809 <https://amzn.to/3vhPCHA>

1/3 yard fusible woven interfacing (20" wide) <https://amzn.to/2N9E1td>

1 set of button snap closure (12.5mm preferably) <https://amzn.to/2DDghc9>

1 keychain ring 1" - 1 1/4" (25 - 32 mm) in diameter <https://amzn.to/2Oni8XR>

## Tools

Basic sewing notions

Polyester thread

watch the video tutorial :  
<https://youtu.be/j0rr35vO3y8>

Finished wallet measurements : 3" x 4 3/4" (7.6 x 12 cm)

### Abbreviation

FWI : Fusible woven interfacing

ST : Stabilizer



Fabric A



Fabric B



Fusible woven  
interfacing  
(FWI)



Stabilizer  
(ST)


Note : Some of the links above are affiliate links; I may earn a small percentage of commission when you make a purchase of qualifying items through any of those links with no additional charge. Thank you for your support!

## Cutting

### Panel 1,2 (pocket panels)


Cut 2x from Fabric B : 18" x 3 1/2" (45.7 x 8.9 cm)

Cut 2x from FWI : 17" x 2 1/2" (43.2 x 6.4 cm)



### Pocket lining



Cut 2x from Fabric B : 3 1/2" x 5 1/2" (8.9 x 14 cm)



### Panel 3 (wallet interior)

Cut 1x from Fabric A : 7" x 5 1/2" (17.8 x 14 cm)



Cut 1x from FWI : 6" x 4 1/2" (15.2 x 11.4 cm)



### Panel 4 (wallet exterior)

Cut 1x from fabric A : 7" x 5 1/2" (17.8 x 14 cm)

Cut 1x from ST : 6" x 4 1/2" (15.2 x 11.4 cm)



### Ring Tab


Cut 1x from fabric A : 2" x 1" (5 x 2.5 cm)



### Button Flap

Cut 1x from fabric A : 5" x 2" (12.7 x 5 cm)

Cut 1x from FWI : 4" x 1" (10 x 2.5 cm)



watch the video tutorial :  
<https://youtu.be/j0rr35vO3y8>


©Copyright 2021 Yoan Sewing Studio

Page 1

## Directions

(these are brief instructions, please refer to the video tutorial for more detailed demonstrations)

1. Apply FWI to the following : Panel 1 & 2, panel 3, flap. Center the position.
2. Apply ST to the Panel 4 (wallet exterior). Center the position.
3. Following the below diagram, draw the pleat lines to the wrong side of panel 1 & 2



4. Fold and press panel 1&2 as instructed in the video. Top stitch the pleat lines.  
Trim the bottom to measure 5 1/2" (14 cm)
5. With the pocket panel 1 and the pocket lining right sides together, sew the right hand side edges with 1/4" (6mm) of seam allowance.  
Press, then topstitch with 1/8" (3mm) of seam allowance.
6. With the pocket panel 2 and the pocket lining right sides together, sew the left hand side edges with 1/4" of seam allowance.  
Press, then topstitch with 1/8" (3mm) of seam allowance.
7. Install the pocket panels to the right side of panel 3.
8. Sew and install the ring tab.
9. Sew the flap.
10. Install the button snap closure.
11. With the panel 3 and panel 4 right sides together, sew all around with 1/2" (1.2 cm) of seam allowance, leave about 3-4" of opening at the bottom.
12. Clip the corners, trim the seam allowances of the sides and the top, (do not trim the seam allowances of the bottom).
13. Turn the wallet right side out through the opening hole. Fold the opening towards the wrong side, clip then press.
14. Finish your wallet with topstitching, then give it a final pressing.

Enjoy your new wallet!

watch the video tutorial :  
<https://youtu.be/j0rr35vO3y8>